



OLTARIS provides the ability to add a human phantom into an uploaded space vehicle shielding distribution, to enable the calculation of whole body effective dose.

The **CAM** (Computerized Anatomical Male) and **CAF** (Computerized Anatomical Female) are established reference body models that are based upon geometric models of the body's tissues.

The phantom tissue distributions for either the CAM or CAF have been pre-calculated and are added to the space vehicle thickness distributions after they are uploaded to OLTARIS.







1 Create CAD shielding model of a space vehicle



2 Download IGES phantoms from OLTARIS



IGES phantoms





3 Place and orient an IGES phantom in the shielding CAD model

To provide the most flexibility, OLTARIS supports a process that allows a user's analysis to reflect the phantom's size, location, and orientation.

CAD-compatible phantom proxies are available to download and import into the space vehicle CAD model.

The phantoms' body tissue distribution is combined with the vehicle shielding distribution after it has been uploaded to OLTARIS.




4 Enter the (x,y,z) locations of the IGES phantom A, B, and C points, using the OLTARIS "Download Rotated Ray Distribution" form, to create and download a ray distribution that matches the phantom orientation




6 Upload Thickness Metafile of vehicle shielding distribution to OLTARIS




Thickness Metafile of ray trace results




5 Use this ray distribution to ray trace the shielding model



Body Phantom proxies are available to download from the OLTARIS web site. The phantom proxies are in an IGES file format that is compatible with any modern CAD program. They include several features designed to make it easy to properly add CAM or CAF distributions to your vehicle shielding distributions.




Each phantom proxy has been created to accurately reflect the outer dimensions and body posture of the CAM and CAF models.




The relative positions of these three points, labeled “A”, “B”, and “C”, uniquely define the orientation of the phantom within the shielding CAD model. Using the locations of these points, OLTARIS will generate a custom ray distribution that will allow it to combine the CAM and CAF distributions with the vehicle shielding distribution.



These five points define the ray tracing target points used for a five-zone full body effective dose calculation. Combined ray trace results from these five points will better capture the variation in the radiation environment inside the space vehicle when compared with results from a single point. The five vehicle distributions will be combined with 500 body tissue distributions by OLTARIS.



Body Phantom ABC Points




Each phantom proxy includes three points, labeled “A”, “B”, and “C”. Once the IGES phantom is oriented inside the space vehicle CAD model, the (x,y,z) locations of the A, B, and C points let OLTARIS generate a custom ray distribution that will allow the CAM and CAF distributions to be properly combined with the vehicle shielding distribution. The point coordinates are entered using the “Download Rotated Ray Distribution” form.


The screenshot shows the OLTARIS web interface. The browser address bar displays http://raadtool.larc.nasa.gov/geometry/orient_ray_distribution. The page header includes the NASA logo and navigation links: Projects, Thickness Distributions, Uncertainty Statement, and User Guides. The main heading is **OLTARIS** with the subtitle "On-Line Tool for the Assessment of Radiation In Space". Below this is a section titled "Select Ray-File and Enter Locator Points".

The "Ray Distribution Files:" dropdown menu is set to "gd10_1002_rays". Below this are input fields for the coordinates of three points:

- Point A:** x = 0.0, y = 0.0, z = 0.0. To the right of these fields is a bracket and the text "Pt. A (x,y,z)".
- Point B:** x = 0.0, y = 0.0, z = 0.0. To the right of these fields is a bracket and the text "Pt. B (x,y,z)".
- Point C:** x = 0.0, y = 0.0, z = 0.0. To the right of these fields is a bracket and the text "Pt. C (x,y,z)".

At the bottom of the form are two buttons: "Download Rotated Ray Distribution" and "Cancel". The footer includes the "FIRSTGOV" logo, links to Freedom of Information Act, The President's Management Agenda, and NASA Privacy Statement, Disclaimer, and Accessibility Certification. It also lists NASA officials: Dr. Chris A. Sandridge (Project Manager), Dr. Lisa C. Simonsen (Website Manager), and Jan Spangler.





Each phantom proxy includes five points spaced along the length of the body. These correspond to five zones that are used in the calculation of the full body effective dose. Roughly 500 body tissue distributions are combined with the vehicle thickness distribution(s) to compute a whole body effective dose.

If the user ray traces their CAD shielding model using each of the 5 zone target points, the 5 thickness distributions that result can be uploaded to OLTARIS, where they will be combined with the 500 CAM/CAF body tissue distributions.

Using multiple vehicle thickness distributions allows OLTARIS' results to better reflect variations in the vehicle's interior radiation environment.

